



Indaver Rivenhall IWMF DCO

Planning Act 2008

Infrastructure Planning (Applications: Prescribed Forms and Procedure)

Regulations 2009

ENVIRONMENTAL STATEMENT [PINS Ref: EN0101038]

ES APPENDIX 8.1: GLOSSARY OF ACOUSTIC TERMINOLOGY

Document Reference: EN0101038/APP/6.2

Revision Number 1.0

APFP Regulation 5(2)(a)

November 2023 Indaver Rivenhall Ltd

Leading the field in sustainable waste management.

Glossary of Acoustic Terminology

In order to assist the understanding of acoustic terminology and the relative change in noise, the following background information is provided.

The human ear can detect a very wide range of pressure fluctuations, which are perceived as sound. In order to express these fluctuations in a manageable way, a logarithmic scale called the decibel, or dB scale is used. The decibel scale typically ranges from 0dB (the threshold of hearing) to over 120dB. An indication of the range of sound levels commonly found in the environment is given in the following table.

| Sound Level | Location |
|-----------------|----------------------------|
| OdB(A) | Threshold of hearing |
| 20 to 30dB(A) | Quiet bedroom at night |
| 30 to 40dB(A) | Living room during the day |
| 40 to 50dB(A) | Typical office |
| 50 to 60dB(A) | Inside a car |
| 60 to 70dB(A) | Typical high street |
| 70 to 90dB(A) | Inside factory |
| 100 to 110dB(A) | Burglar alarm at 1m away |
| 110 to 130dB(A) | Jet aircraft on take off |
| 140dB(A) | Threshold of Pain |

 Table 1

 Sound Levels Commonly Found in the Environment

Acoustic Terminology

- dB (decibel) The scale on which sound pressure level is expressed. It is defined as 20 times the logarithm of the ratio between the root-mean-square pressure of the sound field and a reference pressure (2x10⁻⁵Pa).
- dB(A) A-weighted decibel. This is a measure of the overall level of sound across the audible spectrum with a frequency weighting (i.e. 'A' weighting) to compensate for the varying sensitivity of the human ear to sound at different frequencies.
- L_{Aeq} L_{Aeq} is defined as the notional steady sound level which, over a stated period of time, would contain the same amount of acoustical energy as the A - weighted fluctuating sound measured over that period.
- $L_{10} \& L_{90}$ If a non-steady noise is to be described it is necessary to know both its level and the degree of fluctuation. The L_n indices are used for this purpose, and the term refers to the level exceeded for n% of the time. Hence L_{10} is the level exceeded for 10% of the time and as such can be regarded as the 'average maximum level'. Similarly, L_{90} is the 'average minimum level' and is often used to describe the background noise. It is common practice to use the L_{10} index to describe traffic noise.
- L_{Amax} is the maximum A weighted sound pressure level recorded over the period stated. L_{Amax} is sometimes used in assessing environmental noise where occasional loud

noises occur, which may have little effect on the overall L_{eq} noise level but will still affect the noise environment. Unless described otherwise, it is measured using the 'fast' sound level meter response.

